



Method to add a new printer


Problems may happen during installation, please follow below steps to add a printer when you can not see driver icon shown on devices and printers

1、 Open devices and printers




2、 Click into [add printer], click [Add local printer] then [next]







3、 Chose LPT port as default ,then click [next]




4、 Install driver from Have Disk




5、 Browse C driver as below




6、 Find out file folder name POS PRINTER DRIVER in My Computer C: driver




7、 Chose a right system, 32-bit or 64-bit




8、 Chose INF file




9、Chose [OK]



10、 Chose a corresponding printer type,then click [next]



- 11、 Printer sharing,click[next]



The screenshot shows the 'Add Printer' window with the 'Printer Sharing' section. The window has a title bar with a back arrow, a printer icon, and the text 'Add Printer'. The 'Printer Sharing' section has a blue heading and a paragraph explaining that a share name is required for sharing. There are two radio buttons: 'Do not share this printer' (selected) and 'Share this printer so that others on your network can find and use it'. Below the second radio button are three text input fields labeled 'Share name:', 'Location:', and 'Comment:'. At the bottom right are 'Next' and 'Cancel' buttons.

Printer Sharing

If you want to share this printer, you must provide a share name. You can use the suggested name or type a new one. The share name will be visible to other network users.

☒ Do not share this printer

☐ Share this printer so that others on your network can find and use it


Share name:

Location:

Comment:

Next Cancel

- 12、 Set as fault printer if needed, click [finish] to complete installation



The screenshot shows the 'Add Printer' window with the 'You've successfully added BP-T3' section. The window has a title bar with a back arrow, a printer icon, and the text 'Add Printer'. The 'You've successfully added BP-T3' section has a blue heading and a paragraph explaining that a test page can be printed to check if the printer is working properly. There is a 'Print a test page' button. At the bottom right are 'Finish' and 'Cancel' buttons.


You've successfully added BP-T3

To check if your printer is working properly, or to see troubleshooting information for the printer, print a test page.


Print a test page

Finish Cancel


- 13、 Click and chose printer properties



- 14、 Chose a corresponding port, then click [Apply]



- 15、 Click [General], start testing and click [Print Test Page]



*Once you could print test page, said that driver installed successfully*

*Congratulations and thank you!*